





For this pattern I used my <u>Silver Reed SK840</u> standard electronic knitting machine. I used the ribber for welt, sleeve and neckband.

Pattern Summary

Gauge Swatch

- I did not make any gauge swatch because I wanted a large blouse no matter how it turned out. I let myself be surprised ☺ and I loved the result.

Tension dial - Tension 7, Stitch Dial 3

I used 3 strands of very thin (2 play) nude color combed cotton yarn Nm 2/16.

I consider this blouse to be proper for Size S & M.

The blouse is knitted sideway, following this pattern: 3 working needles, 2 non-working needles (knit 3, slip 2). I knitted it Stockinet, not Slip. I simply put the needles in non-working position.

Legend:

- -K-knit
- NWP non-working position
- -R-row
- LN left needle
- RN- right needle
- Inc increase
- Dec decrease
- Sts stitch
- LNx on Lny transfer LNx on LNy

So the pattern is like this: K3, NWP2, K3, NWP2, ...

Garment Tutorial - Front and Back are identical !!!

The ribber's Half-Pitch Lever must be set to P 5.

On both main bed and ribber, set the stitch dial below 0. Set the carriage at right for Stockinet.

Cast-on for K1 P1 Rib on LN27..RN42 for tighter edge (Broken Toe Cast On). Here is a video tutorial:

http://www.youtube.com/watch?v=zSzparWeh8M

Set stitch dial to 3.

Knit 10 rows.

Transfer all the ribber stitches on the main bed. Now you have all LN27-RN42 needles in working position with stitches on them.

Knit 3 rows.

I explain only the rows on which there are actions to be made, if you do not see a row

specified (like you will not see R3 specified), simply knit the row without any changes.

Set RC to 0.

R1: arrange the needles like this K1, NWP2, K3, NWP2, K3,, K3, NWP2, K1 For the NWP2, since the needles have already stitches on them, move each stitch on the adjacent needle (1 on the adjacent left needle, 1 on the adjacent right needle) to empty them and be able to set them in non-working position.

R2: inc 3 at left using e-wrap method (everytime there is more than 1 sts to increase use the e-wrap method !!!!)

R4: LN30 on LN 29, inc 2 at left

R5: LN31 on LN32, put needles LN30 and LN31 in non-working position; inc 3 at left and inc 1 at right.

R8: LN35 on LN34, inc 2 at left and 1 at right

R9: LN36 on LN37

R10: RN45 on RN44, inc 3 at left and 1 at right

R12: RN46 on RN47, LN40 on LN39, inc 3 at left or 1 at right

R13: LN41 on LN42

R16: LN45 on LN44, inc 3 at left

R17: LN46 on LN47, inc 1 at right

R18: RN50 on RN49, inc 2 at left

R20: RN51 on RN52, LN50 on LN49, inc 3 at left

R21: LN51 on LN52, inc 1 at right

R23: LN55 on LN54, inc 1 at right

R25: LN56 on LN57

R27: LN60 on LN59

R28: RN55 on RN54, inc 1 at right, 2 at left

R29: RN56 on RN57, LN61 on LN62

R31: LN65 on LN64, inc 1 at left

R33: LN66 on LN67, inc 1 at left

R35: LN70 on LN69, inc 1 at right

R36: RN60 on RN59, inc 3 at left

R37: LN71 on LN72, inc 1 at right

R38: RN61 on RN62, inc 3 at left

R39: LN75 on LN74, LN76 on LN77, inc 1 at right

R43: LN80 on LN79 and LN81 on LN82

R46: RN65 on RN64, inc 1 at right and 3 at left

R47: LN85 on LN84 and LN86 on LN87

R48: RN66 on RN67, inc 3 at left and 1 at right

R50: LN90 on LN89, inc 2 at left

R51: LN91 on LN92, inc 1 at right

R54: LN95 on LN94, RN70 on RN69, inc 2 at left

R55: LN96 on LN97, inc 1 at right

R56: RN71 on RN72, inc 3 at left

R64: RN75 on RN74, inc 1 at right

R66: RN76 on RN77, inc 1 at right

R72: RN80 on RN79

R74: RN81 on RN82 R82: RN85 on RN84, inc 1 at right R84: RN86 on RN87 R90: RN90 on RN89 R92: RN91 on RN92, inc 1 at right R100: RN95 on RN94, inc 1 at right R102: RN96 on RN97 R238: RN96 on RN97 R252: inc 1 at right R268: inc 1 at right R274: inc 1 at right R279: dec 1 at right // if you have, for ex, in the right side 3sts, 2slip (therefore 2 nwp), 1sts and you have to descrease the last sts, you simply move it on the adjacent left needle which is empty (you bring it from non-working position, and so on with the next) R281: dec 1 at right R283: dec 1 at right R284: dec 1 at right R286: dec 1 at right R288: dec 1 at right R290: dec 1 at right R292: dec 1 at right R293: dec 1 at right R295: dec 1 at right R297: dec 1 at right R299: dec 1 at right R301: dec 1 at right R302: dec 1 at right R304: dec 1 at right R306: dec 1 at right R308: dec 1 at right R309: dec 1 at right R311: dec 1 at right R313: dec 1 at right R315: dec 1 at right R317: dec 1 at right R318: dec 1 at right R320: dec 1 at right R322: dec 1 at right R324: dec 1 at right R326: dec 1 at right R327: dec 1 at right R328: dec 3 at left R329: dec 1 at right

R330: dec 2 at left R331: dec 1 at right R332: dec 3 at left R333: dec 1 at right

```
R334: dec 2 at left
R335: dec 1 at right
R336: dec 3 at left, dec 1 at right
R338: dec 3 at left, dec 1 at right
R340: dec 2 at left, dec 1 at right
R342: dec 3 at left, dec 1 at right
R344: dec 2 at left, dec 1 at right
R345: dec 1 at right
R346: dec 3 at left
R347: dec 1 at right
R348: dec 3 at left
R349: dec 1 at right
R350: dec 2 at left
R351: dec 1 at right
R352: dec 3 at left
R353: dec 1 at right
R354: dec 2 at left, dec 1 at right
R356: dec 3 at left, dec 1 at right
R358: dec 3 at left, dec 1 at right
R360: dec 2 at left, dec 1 at right
R361: dec 1 at right
R362: dec 3 at left
R363: dec 1 at right
R364: dec 3 at left
R365: dec 1 at right
R366: dec 2 at left
R367: dec 1 at right
R368: dec 3 at left
R369: dec 1 at right
R370: dec 2 at left, dec 1 at right
R372: dec 3 at left, dec 1 at right
R374: dec 3 at left, dec 1 at right
R376: dec 2 at left, dec 1 at right
R378: dec 3 at left, dec 1 at right
R379: dec 1 at right
R380: dec 2 at left
```

Before the next row, all needles must be in working position having sts on them, so, for those empty on NWP, you simply move the heel of the sts from the adjacent needle onto them (like for Fashion Increase). You do this for all the remaining nwp needles.

R383: knit all R384: knit all R385: knit all

R381: dec 1 at right R382: dec 3 at left

Before the next row, transfer every other sts on the ribber for K1 P1 rib.

Knit 10 rows.

Cast off.

End of the piece.

Neckband:

I put the piece back on the machine (with the wrong side facing you) with the part where is knitted the neckband (now the piece is not sideway). Do not stretch it, pick the stitches naturally. I used pretty much every other whole and in the end I had 88 sts on the machine. Transfer every other sts on the ribber for a K1 P1 rib.

Knit 30 rows.

Transfer all the ribber stitches to the main bed.

Knit one more row with stitch dial set to 8 and cast off.

Welt:

Put the piece back on the machine (with the bottom part, where is knitted the welt), wrong side facing you. Again, not not stretch. In the end I had 135 sts on the machine. Follow the neckband instructions.

Knit the same the other piece.

Sew the pieces together and there you have the blouse.