

Constraints on source properties of low-frequency earthquakes (LFEs) in Parkfield and Cascadia

Amanda M. Thomas
SCEC, 9/13/2016




Slow vs. fast earthquakes

Fast earthquakes


have durations of fractions of a second to a few minutes.

Slow earthquakes have durations of fractions days, weeks, months and even years.




Tremor and low-frequency earthquakes

Tremor is an unusual seismic signal....




Tremor and low-frequency earthquakes

Tremor is an unusual seismic signal....





...that can be explained as a superposition of small earthquakes.



Low-frequency earthquakes

Properties of LFEs:

- 1) Depleted in high frequency content relative to traditional earthquakes of similar magnitude
- 2) Reflect slip on asperities that rupture repeatedly in response to surrounding slow slip
- 3) Never get large




Moment-duration scaling


Seismic moment is a measure of earthquake size (similar to magnitude)

$$M_0 = \mu A d$$


Moment $\rightarrow M_0$
Rigidity $\rightarrow \mu$
Area $\rightarrow A$
Displacement $\rightarrow d$



What is an LFE?





- × non-RTR detections
 - × RTR detections
 - × LFEs as reported in *Rubin et al, 2013*
 - ◇ LFE template locations
 - slab model from *Audet et al, 2010*
- non-RTR Direction and velocity of non-RTR front and RTRs
RTR



What is an LFE?

PROPERTY	<u>EARTHQUAKES</u>	<u>LFEs</u>
DURATION (M=1)	~0.01 s	
<i>b</i> -VALUE	1	
MOMENT-DURATION SCALING	$M \sim D^3$	
SELF SIMILARITY	YES	

Parkfield LFEs



Source seismology


RECORDED
GROUND
MOTION

SOURCE

PATH

SITE

$$u(t) = s(t) * g(t) * i(t)$$



Source seismology


RECORDED
GROUND
MOTION

SOURCE

PATH

SITE

$$u(t) = s(t) * \cancel{g(t)} * \cancel{v(t)}$$



Source seismology

TARGET
EVENT
GROUND
MOTION

SOURCE

PATH

SITE

$$u = s(t) * g(t) * i(t)$$

eGF
GROUND
MOTION


SOURCE


PATH

SITE

$$u = s(t) * g(t) * i(t)$$

If the eGF source duration is short relative to the target event then...


$$s(t) \approx \text{[impulse function]}$$




eGf analysis applied to LFEs

Requirements for eGf analysis:


- 1) The earthquakes are "close"
- 2) They have the same focal mechanism
- 3) Their durations are substantially different (i.e. the eGf doesn't contain a strong signature of its own source complexity)



eGf analysis applied to LFEs

Requirements for eGf analysis:


- 1) The earthquakes are "close"
- 2) They have the same focal mechanism
- 3) Their durations are substantially different (i.e. the eGf doesn't contain a strong signature of its own source complexity)



eGf analysis applied to LFEs

Requirements for eGf analysis:

- 1) The earthquakes are "close"
- 2) They have the same focal mechanism
- 3) Their durations are substantially different (i.e. the eGf doesn't contain a strong signature of its own source complexity)





Waveforms and spectra

B

Station SMNB

eGf: 21404575



LFE: 37102



Station FROB

eGf: 21526604


LFE: 37140



Modified eGf analysis


PATH + SITE

SMNB-DP3



SOURCE

Example Hann
window
source-time
function




SYNTHETIC

7.09





COMPARISON

0.71



3 seconds

LFE duration






Duration= ~ 0.2 s

What is an LFE?

PROPERTY	<u>EARTHQUAKES</u>	<u>LFEs</u>
DURATION (M=1)	~0.01 s	~0.2 s
<i>b</i> -VALUE	1	
MOMENT-DURATION SCALING	$M \sim D^3$	
SELF SIMILARITY	YES	

Cascadia LFEs




Estimating moment

RECORDED
GROUND
MOTION

$$u = s(t) * g(t) * i(t)$$

SOURCE **PATH** **SITE**



Estimating moment

Displacement u
at position \underline{x} as a
function of time t

Intrinsic
attenuation

Source radiation
pattern

$$u_i(\mathbf{x}, t) = A(\mathbf{x}, \mathbf{x}') E(\mathbf{x}, \mathbf{x}') F_{ij}(\mathbf{x}, \mathbf{x}') R_j(\mathbf{x}, \mathbf{x}') \dot{M}_0(t - \tau(\mathbf{x}, \mathbf{x}')),$$


Material properties,
transmission coefficients,
and geometric spreading.

Free
surface
amplification


Source-time
function

Waveforms

Template: 001 - P




moment



b-values

Fast earthquakes


1976-2005 Global CMT catalog




b-values

Fast earthquakes

1976-2005 Global CMT catalog



LFEs



What is an LFE?


PROPERTY	<u>EARTHQUAKES</u>	<u>LFEs</u>
DURATION (M=1)	~0.01 s	~0.2 s/~0.5 s
<i>b</i> -VALUE	1	4+
MOMENT-DURATION SCALING	$M \sim D^3$	
SELF SIMILARITY	YES	

Moment-duration scaling

Seismic moment is a measure of earthquake size (similar to magnitude)

$$M_0 = \mu A d$$

Moment \rightarrow M_0
Rigidity \rightarrow μ
Area \rightarrow A
Displacement \rightarrow d



LFE moment-duration scaling

Fast earthquakes


$$M_0 \propto T^3$$

Slow earthquakes

$$M_0 \propto T$$

LFEs

$$M_0 \propto T^{10}$$




What is an LFE?


PROPERTY	<u>EARTHQUAKES</u>	<u>LFEs</u>
DURATION (M=1)	~0.01 s	~0.2 s/~0.5 s
<i>b</i> -VALUE	1	4+
MOMENT-DURATION SCALING	$M \sim D^3$	$M \sim D^{10}$
SELF SIMILARITY	YES	

How are moment changes accommodated?

Small Moment



Large Moment






How are moment changes accommodated?


Large Moment

Small Moment

Small Moment



Large Moment



Observations:


1. Duration ratio: b_{\parallel}
2. Amplitude ratio: $b_{\text{perp}} b_D$

How are moment changes accommodated?

Large Moment




Small Moment

Small Moment



$\times b_{\parallel}$


Large Moment



Observations:

1. Duration ratio: b_{\parallel} (1.29)
2. Amplitude ratio: $b_{\text{perp}} b_D$ (9.49)

Near source attenuation?



Observations:



- 1) Intraslab EQs with overlapping and similar paths retain high frequency content
- 2) Intraslab EQs are more severely attenuated due to transit through a low-Q layer at the top of the oceanic crust [Yabe et al. 2014]

What is an LFE?


PROPERTY	<u>EARTHQUAKES</u>	<u>LFEs</u>
DURATION (M=1)	~0.01 s	~0.2 s/~0.5 s
<i>b</i> -VALUE	1	4+
MOMENT-DURATION SCALING	$M \sim D^3$	$M \sim D^{10}$
SELF SIMILARITY	YES	NO

What is an LFE?


- LFE duration represents rupture duration, assuming constant rupture velocity this reflects a length scale
- Moment duration scaling suggests LFEs have nearly constant size
- LFEs are severely spatially confined
- Low effective stress limits the LFE stress drop, and can explain why LFEs never become large magnitude



What is an LFE?




Constant patch size across 100s of kms along strike, 10s of kms along dip, and multiple subduction zones?



Speculometer




-- not very speculative




-- somewhat speculative



-- speculative



-- very speculative



Estimating moment (2)

- Correct for free surface and make corrections to attain moment estimate
- Still significant sources of error due to anisotropy, etc.
- Assume a multiplicative path term that relates the true moment to the measured moment

$$\log M_0^{IJ} = \log M_0^I + \log S^J.$$

$$\sum_J \log S^J = 0.$$

$$M_0 = \frac{\int dt \dot{u}_j(\mathbf{x}, t)}{A(\mathbf{x}, \mathbf{x}') E(\mathbf{x}, \mathbf{x}') R_j(\mathbf{x}, \mathbf{x}')},$$

